

How to manage authenticators



A user must have relevant access rights to be able to manage authenticators.

If you would like to manage authenticators, please open the **Authenticators** tab in the user profile. The tab shows the number of registered user authenticators and their parameters.

[MC](#) / [Users](#) / [James Miller](#) / [Authenticators](#)

James Miller - Authenticators

General information	<div><div><div><div><div></div><div>Register</div></div><div></div></div><div><div><div>Unlock</div></div><div></div></div><div><div><div>Allow use</div></div><div></div></div><div><div><div>Deny</div></div><div></div></div></div></div>						
Applications							
Authenticators							
Sign in history							
Licenses							
		AUTHENTICATOR TYPE	DEVICE	NOTE	REGISTERED DATE	ENROLLED BY	STATUS
<div><div><div></div></div><div><div>MFA</div></div></div>	<div><div></div><div>Multi-factor authentication</div></div>	Windows Password + Futronic	BSP for Multi-factor authentication				Is acting
<div><div><div></div></div><div><div>***</div></div></div>	<div><div></div><div>Passcode</div></div>	Passcode		2020.09.15 15:56	James Miller		Is acting
<div><div><div></div></div><div><div>***</div></div></div>	<div><div></div><div>Windows Password</div></div>	Windows Password	Windows Password				Is acting

How to disable an authenticator

1. Select a relevant authenticator.
2. Click **Deny**.

[MC](#) / [Users](#) / [James Miller](#) / [Authenticators](#)

James Miller - Authenticators

General information

Applications

Authenticators

Sign in history

Licenses

+ Register

Unlock

Allow use

Deny

Authenticator type	Device	Note	Registered date	Enrolled by	Status
<div><div><div></div></div><div>MFA</div></div> <div>Multi-factor authentication</div>	Windows Password + Futronic	BSP for Multi-factor authentication			Is acting
<div><div><div></div></div><div>***</div></div> <div>Passcode</div>	Passcode		2020.09.15 15:56	James Miller	Is acting
<div><div><div></div></div><div>***</div></div> <div>Windows Password</div>	Windows Password	Windows Password			Is acting

3. Once an authenticator has been disabled, users will not be able to use this login method. The authenticator status will be changed to **Forbidden**.

<input type="checkbox"/>	Passcode	Passcode	2020.09.15 15:56	James Miller	Forbidden
--------------------------	----------	----------	------------------	--------------	-----------

How to enable an authenticator

1. Select a relevant authenticator.
2. Click **Allow use**.

+ Register
Unlock
Allow use
Deny

	AUTHENTICATOR TYPE	DEVICE	NOTE	REGISTERED DATE	ENROLLED BY	STATUS
<input type="checkbox"/>	MFA Multi-factor authentication	Windows Password + Futronic	BSP for Multi-factor authentication			Is acting
<input checked="" type="checkbox"/>	Passcode	Passcode		2020.09.15 15:56	James Miller	Forbidden
<input type="checkbox"/>	Windows Password	Windows Password	Windows Password			Is acting


3. Once an authenticator has been enabled, users will have the option to use this login method. The authenticator status will be changed to **Is acting**.

<input type="checkbox"/>	Passcode	Passcode	2020.09.15 15:56	James Miller	Is acting
--------------------------	----------	----------	------------------	--------------	-----------


How to register an authenticator

i Email and SMS providers do not require registration and can be used if a user has indicated their email address or phone number, respectively. If relevant parameters have not been set, authenticators will not appear on the list of available user authenticators.

1. Click **Register** and select a relevant login method from the drop-down list.

 If a user has reached the limit in terms of permitted number of authenticators that can be registered for a given login method, such method will not appear on the list.

2. Please follow these steps to train an authenticator.

 The training algorithm for different authenticators may vary and different windows may appear.

 Save  Cancel

Passcode

Password*

.....

Confirm password*

.....

Comment

Passcode 2

3. After successful registration, the authenticator status will be changed to **Is acting**.

<input type="checkbox"/>	***	Passcode	Passcode	Passcode 2	2020.09.15 16:24	James Miller	Is acting
--------------------------	-----	----------	----------	------------	------------------	--------------	-----------

4. If a provider with registered authenticators has been deleted, the authenticator status will be changed to **Not installed**.

<input type="checkbox"/>	***	Passcode	Passcode	Passcode 2	2020.09.15 16:24	James Miller	 Not installed
--------------------------	-----	----------	----------	------------	------------------	--------------	---

How to delete an authenticator

1. Select an authenticator and click **Delete**.

MC / Users / James Miller / Authenticators

James Miller - Authenticators

General information

Applications

Authenticators

Sign in history

Licenses

+ Register

Delete

Unlock

Allow use

Deny

AUTHENTICATOR TYPE	DEVICE	NOTE
<div><div><input type="checkbox"/></div><div>MFA</div></div> <div>Multi-factor authentication</div>	Windows Password + Futronic	BSP for Multi-factor authenticati
<div><div><input type="checkbox"/></div><div>***</div></div> <div>Passcode</div>	Passcode	
<div><div><input checked="" type="checkbox"/></div><div>***</div></div> <div>Passcode</div>	Passcode	Passcode 2
<div><div><input type="checkbox"/></div><div>***</div></div> <div>Windows Password</div>	Windows Password	Windows Password

2. Confirm that you wish to delete this item.

Confirmation

Are you sure you want to delete selected items?

Cancel

Delete